

# One■Leg Hexapod — Serial Command Reference

## Connection

- Board: Arduino Mega 2560
- Port: USB (Arduino IDE → Tools → Port)
- Baud: 115200 • Line ending: Newline (\n)
- Library: Adafruit PWM Servo Driver (PCA9685)

## Top■Level Commands (type then press Enter)

cal — Enter calibration mode

test — Run the sample motion sequence

## Calibration Mode Commands

c+ / c- — Nudge Coxa zero by +1 / -1 degree (auto■centers to 90° when adjusted)

f+ / f- — Nudge Femur zero by +1 / -1 degree (auto■centers to 90° when adjusted)

t+ / t- — Nudge Tibia zero by +1 / -1 degree (auto■centers to 90° when adjusted)

save — Store current offsets to EEPROM

exit — Leave calibration mode

## Recommended Workflow

- 1) Power servos (UBEC → PCA9685 V+) and connect USB to the Mega.
- 2) Open Serial Monitor (115200 baud, newline), type 'cal'.
- 3) Use c+/c-, f+/f-, t+/t- to center each joint mechanically at 90°.
- 4) Type 'save' to write offsets to EEPROM, then 'exit'.
- 5) Type 'test' to verify smooth motion; adjust offsets if required.

## Notes & Safety

- Keep the leg supported during first power■up to avoid unexpected swings.
- Ensure common ground between UBEC, PCA9685, servos, and Arduino.
- Typical servo range is ~0–180°. Code clamps angles to protect hardware.
- If servos chatter, verify UBEC voltage (5–6 V) and add the 2200 µF cap at PCA input.
- Re■run 'cal' after any mechanical changes (horn re■position, linkage changes).